

Using Phase Manager 4 and 5 concurrently

If you already are a user of Phase Manager 4 and you are updating to Phase Manager 5, you can use each program separately.

In order to do that, you must modify the licence folder of Phase Manager 5 during the setup. Please imperatively follow the tutorial below.

Setting up Phase Manager 5

* Download the setup using the link in your email or using this following link


https://docs.phasemanager.com/1-installation/0-a-setups-download

* Run the setup and once installation is complete, follow the tutorial below before launching Phase Manager 5 for the first time.

License configuration and modifying the license folder

* Once Phase Manager 5 is installed, double-click on its icon to launch it. At first launch, the license configurator will display.

Please pay attention from now on, especially on the "License" menu.



To activate your license, you will need to fill in the following fields:

Module

Choose the type of license you have :

- * Monoposte = Standalone
- * Réseau = Network
- * USB = install on a USB Key

	Licensing Configuration
Module	Monoposte 🔹

Product ID

Fill in the Product ID that's been sent to you by Projet Linéaire:

- licence pattern : LPMM-00NNN0500abcDEF (NNN is the number of your license, and 5 the version)
- only paste the right part of your Product-ID, after the '-' :

Module	Monoposte	•
Product ID	LPMM	00NNN0400abcDEF

Activation key

Fill in the Serial number sent to you by Projet Linéaire.

* pattern : VccQX-37eJG-AZIce-EYk7O-temCP-8DRFu

Module	Monoposte 💌	
Product ID	LPMM	00NNN0400abcDEF
Activation	XkcQs-ABCDE-AZHcN-12345-oemCP-zycba	

License

Choose "Create new licence" :

Create new licence
Choose a licence

Here is where you have to change the license folder.

Indeed, the program wil choose by default the following path :

(C:\Users\Public\Documents\PhaseManager-Licence), but this folder already contains your Phase Manager 4 license. If we do not modify the folder, the Phase Manager 5 program will crush and replace the license and you will not be able to use Phase Manager 4 anymore.

Module	Monoposte 👻		
Product ID	LPMM 00NNN0400abcDEF		
Activation	XkcQs-ABCDE-AZHcN-12345-oemCP-zycba		
Create new licence Choose a licence			
Browse	C:\Users\Public\Documents\PhaseManager-Lice		

In order to do that, click on the "Browse" button and choose another folder for the Phase Manager 5 license. I suggest you to create a new folder named "PhaseManager5-Licence" in this following folder "C:\Users\Public\Documents" and be sure to choose the new folder you just created.

Once you have choose the new folder you created for you Phase Manager 5 license, you can just click on the "Launch" Button to active it, and follow the setup tutorial.

For a network License

The installation is the same as above, just make sure you install the network license in another folder (different from the PM4 current one).