

## Connection to a Network license V5


**Caution:**

1/ **Connecting to a network license requires that it has already been activated by following the procedure [Activating a network license](#)**

2/ **To use the license it is necessary to have **MODIFY** rights on the **UNC license directory****

### 1/ Installation of Phase Manager


Run the setup and choose the installation language:



Skip the welcome screen by clicking on **Next** :



Accept the license agreement then click on **Next** :

**License Agreement** 

Please read the following important information before continuing.

Please read the following License Agreement. You must accept the terms of this agreement before continuing with the installation.

LICENCE D'UTILISATION  
DU LOGICIEL PHASE MANAGER

Article 1 - Objet des présentes conditions générales  
Les présentes conditions générales ont pour objet de préciser les conditions dans lesquelles l'EDITEUR PROJET LINEAIRE DEVELOPPEMENT concède à l'UTILISATEUR un droit d'utilisation du LOGICIEL PHASE MANAGER et assure la maintenance dudit LOGICIEL PHASE MANAGER.

Article 2 - Utilisation du LOGICIEL PHASE MANAGER  
Le LOGICIEL PHASE MANAGER s'adresse à des utilisateurs confirmés ou non, travaillant sur un environnement Windows uniquement (Vista ou supérieur).


I accept the agreement  
 I do not accept the agreement

< Back   **Next >**   Cancel

Destination location : we **recommend you keep the default path**:



Choose '**Single user installation**'


**Select Components** 

Which components should be installed?


Select the components you want to install; clear the components you do not want to install. Click Next when you are ready to continue.

**Single user installation** ▾

Validate the Start Menu Folder screen by clicking on **Next** :



Choose and validate the icons creation screen by clicking **Next** :




On the following screen click on **Install** then once installation is complete, click on **Finish**

---

## 2/ Connection to the network license

Once Phase Manager V5 is installed, double-click on its icon to launch it.  
At first launch, the license configurator will display:



To connect to your network license, you will need to fill in the following fields:

## Module

Choose **Réseau**:

Module	<b>Réseau</b> ▼
--------	-----------------

## Product ID

Fill in the Product ID that's been sent to you by Projet Linéaire:

- licence pattern : LPMM-00**NNN**0500abcDEF (**NNN** is the number of your license, and **5** the version)
- **only paste the right part of your Product-ID, after the '-' :**

Module	<b>Réseau</b> ▼	
Product ID	LPMP	<b>00NNN0400abcDEF</b>

## Activation key

Fill in the Serial number sent to you by Projet Linéaire.

- pattern : VccQX-37eJG-AZlce-EYk7O-temCP-8DRFu

Module	Reseau	
Product ID	LPMP	00NNN0400abcDEF
Activation...	VccQX-37eJG-AZlce-EYk7O-temCP-8DRFu	

## Licence

Choisir "Choose a licence" :  Create new licence  Choose a licence

By clicking on the  button, indicate the location of the license file:

Indicate its UNC path using the following pattern : **\\SERVER\SHARE\FOLDER:**

Module	Reseau	
Product ID	LPMP	00NNN0400abcDEF
Activation...	VccQX-37eJG-AZlce-EYk7O-temCP-8DRFu	
Create new licence	<input type="radio"/>	Choose a licence <input checked="" type="radio"/>
<input type="button" value="Browse"/>	\\PI-sv\Share\Shared-Licence	

Click now on the  button to run Phase Manager.

- If you need to, feel free to contact our customer support at [support@projetlineaire.com](mailto:support@projetlineaire.com)